



• bond-buzz free e-newsletter
• product information
• free projects

shop
online
now!

what's new • for the cause • clubs • help • contact us

ultimate sweater
machine®

wyr knitter™

embellish-knitter™

pocket knitter™

Send this page to a friend
Enter your friend's e-mail
address:

We will not share or
keep this e-mail address.

Share

Bond America
is a division of

CARON

www.caron.com

Proud sponsor of

Rwanda Knits

www.fiberandcraft.org

For the Ultimate Sweater Machine®

Paillette-Edged Scarf & Purse

designed by Kathy Perry



EASY

TECHNIQUE USED

Paillettes added to purl side of fabric.

FINISHED MEASUREMENT

Approx 5"/12.5 cm wide x 60"/152 cm long

YARN

[Caron International's Simply Soft®](#) (100% acrylic,
6oz/170g, 315yds/288m): Shown in: #0013 Nutmeg 6
oz/170g



For more technique info
see Bond Buzz #68

[Printer Friendly PDF](#)

KEY PLATE

USM/ISM KP#4 or appropriate tension to obtain gauge
Suitable for USM/ISM/Bond Classic or 6.5 to 9 mm knitting machine

ADDITIONAL MATERIALS

400 bronze paillettes (20 mm with 5 mm hole)
WY
Yarn needle

OPTIONAL

Row counter

GAUGE

In Stockinette stitch with KP #4, 15 sts and 16 rows = 4"/10 cm

KNIT STITCHES USED

Stockinette stitch (St st)

NEEDLES REQUIRED 43

NOTE: Scarf is made in two pieces and joined at center back.

SCARF (Follow technique instructions for placing
paillettes on PURL side of fabric.)

- Using closed CO method, CO 43 sts. COR.
RC=000. Leave long end for sewing back
seam.
- K 2 R.
- Paillettes: Following technique instructions,
*work across row placing paillettes on every
other ndl. Do not place on very end ndls. K 2
R. Work across row *staggering* paillettes on
every other ndl. Do not place on 2 end ndls on
ea side. K 2 R. Repeat from * to RC=020.



- Take work off machine on WY but do not cut yarn. Turn piece over and rehang so paillettes are facing back.
- COL. Set RC to 000. K to RC=096 and cut yarn leaving long piece for seaming or grafting. Take work off on WY.
- Make second piece in same manner (leaving long ends is not necessary).



FINISHING

- Seam or graft two pieces together.
- Weave in ends.
- Sew center back seam. Tack bottom ends closed.

PURSE WITH PAILLETTE FLAP

designed by Kathy Perry



INTERMEDIATE

TECHNIQUE USED

Paillettes added to purl side of fabric.

FINISHED MEASUREMENT

Approx 8"/20.5 cm wide x 9"/23 cm long

YARN

[Caron International's Simply Soft®](#) (100% acrylic, 6oz/170g, 315yds/288m): Shown in: #0013 Nutmeg
4oz/115g



KEY PLATE

USM/ISM KP #4 (purse flap only) and KP #2.5 or appropriate tension to obtain gauge
Suitable for USM/ISM/Bond Classic or 6.5 to 9 mm knitting machine

ADDITIONAL MATERIALS

100 bronze paillettes (20 mm with 5 mm hole)
Single prong transfer tool
WY
Yarn needle
1/3 yard lining fabric
Snap or flap closure
Sewing needle and matching thread
Optional: Felt or batting for inner lining

OPTIONAL

Row counter

GAUGE

In Stockinette stitch with KP #2.5, 17 sts and 22 rows = 4"/10 cm

KNIT STITCHES USED

Stockinette stitch (St st)

NEEDLES REQUIRED 47

PURSE (Follow technique instructions for placing paillettes on PURL side of fabric.)

- Using closed CO method and KP #4, CO 13 sts. COR. RC=000.
- K 2 R.
- Shape flap: Inc 1 st ea side ER 10 times to 33 sts. (NOTE: On paillette rows, inc sts before hanging paillettes.)
- Paillettes: AT SAME TIME, following technique instructions, *work across row placing

paillettes on every other ndl. Do not place on very end ndls. K 2 R. Work across row *staggering* paillettes on every other ndl. (To keep staggered pattern, do not place on either 1 or 2 end ndls on ea side.) K 2 R. Repeat from * to RC=018.

- Take work off machine on WY but do not cut yarn. Turn piece over and rehang so paillettes are facing back.
- Purse body: Change to KP #2.5. COL. Set RC to 000. Inc 7 sts beg next 2 rows - 47 sts. K to RC=094.
- BO.

FINISHING

- Weave in ends.
- Fold sides of purse to inside and tack down using needle and thread. (Optional: Lay a piece of felt or batting between the folded sides for extra body. Tack lightly in place.)
- Lining. Open paillette flap so purse is one straight piece. Cut lining the size of the purse, allowing 1/2"/1.25 cm extra on all sides. Turn the 1/2"/1.25 cm lining allowance to wrong side and iron down. Pin lining to purse with wrong sides together and sew using needle and thread.
- Fold up bottom of purse and pin sides so that flap folds properly in place. Seam sides.
- Make a 50-60"/127-152.5 cm twisted cord, braid or l-cord for strap and tack in place on sides and bottom of purse.
- Add snap or other closure to flap.

Subscribe to Bond-Buzz, our free e-newsletter.

Enter your e-mail address

We respect your privacy. We will not share your e-mail address with others.

[online store](#) • [products](#) • [projects](#) • [what's new](#) • [for the cause](#) • [bond-buzz](#) • [clubs](#) • [help](#) • [contact us](#)

© Caron International 2003-2010